

Printer Driver Installation procedure (For download package) (For Windows® CP-D70DW series)

This document is a supplement to the PRINTER DRIVER GUIDE for Windows®CP-D70DW series.

The “PRINTER DRIVER GUIDE” is in the CD pack with the printer.

Please download the printer driver from

<http://www.MitsubishiElectric.co.jp/vcp/>.

You may store the file since the driver is not included with the supplied CD.

Use the appropriate printer driver base on your operating system requirement:

CPD70X : Windows XP

CPD70V : Windows Vista and Windows 7

Installation

1. Windows XP

1.1. Installing the USB port

Refer to the section 1.1 of PRINTER DRIVER GUIDE

1.2. Installing the driver

Skip step 1(the insertion of CD-ROM), then proceed to step 2 and 3.

At step 4, select “Include this location in the search” and click “Browse” to locate the folder where the printer driver is stored, then click “Next” button.

Continue to step 5 to finish installation.

2. Windows Vista

2.1. Installing the USB port

Refer to the section 2.1 of PRINTER DRIVER GUIDE


2.2. Installing the driver

Skip step 1(the insertion of CD-ROM) and proceed to step 2. Click “Continue” button on “User Account Control”.


Then follow these steps:

- i) Select "I don't have the disc. Show me other options."<Fig1>
- ii) Select "Browse my computer for driver software".<Fig2>
- iii) Click "Browse" then "Browse to locate the folder where the printer driver is stored
and click "Next" button. <Fig3>


Continue to step 3 to finish installation.



<Fig.1>



<Fig.2>



<Fig.3>

3. Windows 7

3.1. Installing the driver

Follow step 1 to 6 of the PRINTER DRIVER GUIDE.

At step 7, make sure that selected Processor is suitable for your PC.

Then proceed to step 8 to finish the installation.

Uninstallation

Refer to "Uninstallation" section of PRINTER DRIVER GUIDE and follow the steps below.

1. Windows XP

Instead of step 1 for inserting the CD-ROM, locate and open the folder of your PC where the printer driver was stored and execute "Rem70.exe."

Continue the procedure from step 3 to complete the uninstallation.

2. Windows Vista, Windows 7

Refer to PRINTER DRIVER GUIDE